Overview Package Class Use Tree Deprecated Index Help

PREV CLASS NEXT CLASS
SUMMARY: NESTED | FIELD | CONSTR | METHOD

FRAMESNO FRAMESAll ClassesDETAIL: FIELD | CONSTR | METHOD

stamp.peripheral.onewire

Class DS2480B

public class **DS2480B** extends <u>Object</u>

Overview

The DS2480B chip is a transceiver that the Javelin Stamp can use to communicate with devices on a 1-Wire bus. Each instance of the DS2480B library supports communication between the Javelin Stamp and a DS2480B chip.

See Also:

Getting Started with 1-Wire for circuit diagrams, examples, and instructions on how to use this class with the DS2480B and devices on a 1-Wire bus. This application note is available from www.javelinstamp.com.

Field Summary			
static int	To send a binary-0 to the 1-Wire bus, place the DS2480B in command mode, then use the message method to send this value.		
static int	To send a binary-1 to the 1-Wire bus, place the DS2480B in command mode, then use the message method to send this value.		
static int	To place the DS2480B into command mode, use the message method to send it this value.		
static int	To place the DS2480B into data mode, use the message method to send it this value.		
static int	To enable the DS2480B's strong pullup resistor, pass this value to the strongPullup method.		

static int	The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-0 from the Javelin Stamp (BIT_WRITE_0) to the 1-Wire bus and received a binary-0 reply.
static int	The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-1 from the Javelin Stamp (BIT_WRITE_1) to the 1-Wire bus and received a binary-0 reply.
static int	The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-0 from the Javelin Stamp (BIT_WRITE_0) to the 1-Wire bus and received a binary-1 reply.
static int	The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-1 from the Javelin Stamp (BIT_WRITE_1) to the 1-Wire bus and received a binary-1 reply.
static int	SEARCH_ACCELERATOR_OFF To disable the DS2480B's search accelerator mode, place it into command mode, then use the message method to send it this value.
static int	SEARCH_ACCELERATOR_ON To enable the DS2480B's search accelerator mode, place it into command mode, then use the message method to send it this value.
static int	TERMINATE DURATION To disable the DS2480B's strong pullup resistor, pass this value to the strongPullup method.

Constructor Summary

DS2480B(int txPin, int rxPin)

Constructs a Uart to 1-Wire serial interface using the specified I/O pins for Uart communication between the DS2480B and the Javelin Stamp.

Meth	Method Summary				
boolean	getBit() Reads a bit value from the 1-Wire bus.				
void	getData(int bytecount, int[] array, int command) Retrieves data bytes from the 1-Wire bus and stores them in an array.				
void	message(int b) Sends a byte to the DS2480B.				
void	message (int b, int c) Sends a two message bytes to the DS2480B.				
void	<pre>message(int number, int[] values) Sends a specified number of message bytes from an array of int values.</pre>				
void	message (int b, int c, int d) Sends a three message bytes to the DS2480B.				

	boolean	reset() Sends a reset pulse to the DS2480B's 1-Wire bus.
Ī	void	<pre>strongPullup(int parameter) Enables or disables the DS2480B's 4.7 k "strong pullup resistor".</pre>

Methods inherited from class java.lang.Object	
---	--

equals

Field Detail

COMMAND

public static final int COMMAND

To place the DS2480B into command mode, use the message method to send it this value.

See Also:

Constant Field Values

DATA

public static final int DATA

To place the DS2480B into data mode, use the message method to send it this value.

See Also:

Constant Field Values

INFINITE_DURATION

public static final int INFINITE_DURATION

To enable the DS2480B's strong pullup resistor, pass this value to the strongPullup method.

See Also:

Constant Field Values

TERMINATE_DURATION

public static final int TERMINATE_DURATION

To disable the DS2480B's strong pullup resistor, pass this value to the strongPullup method.

See Also:

Constant Field Values

BIT_WRITE_1

public static final int BIT_WRITE_1

To send a binary-1 to the 1-Wire bus, place the DS2480B in command mode, then use the message method to send this value.

See Also:

Constant Field Values

BIT_WRITE_0

public static final int BIT_WRITE_0

To send a binary-0 to the 1-Wire bus, place the DS2480B in command mode, then use the message method to send this value.

See Also:

Constant Field Values

READ_1_WROTE_1

public static final int READ_1_WROTE_1

The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-1 from the Javelin Stamp (BIT_WRITE_1) to the 1-Wire bus and received a binary-1 reply.

See Also:

Constant Field Values

READ_0_WROTE_1

```
public static final int READ 0 WROTE 1
```

The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-1 from the Javelin Stamp (BIT_WRITE_1) to the 1-Wire bus and received a binary-0 reply.

See Also:

READ_1_WROTE_0

public static final int READ_1_WROTE_0

The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-0 from the Javelin Stamp (BIT_WRITE_0) to the 1-Wire bus and received a binary-1 reply.

See Also:

Constant Field Values

READ_0_WROTE_0

public static final int READ_0_WROTE_0

The DS2480B replies to the Javelin Stamp with this value if it relayed a binary-0 from the Javelin Stamp (BIT_WRITE_0) to the 1-Wire bus and received a binary-0 reply.

See Also:

Constant Field Values

SEARCH_ACCELERATOR_ON

public static final int SEARCH_ACCELERATOR_ON

To enable the DS2480B's search accelerator mode, place it into command mode, then use the message method to send it this value.

See Also:

Constant Field Values

SEARCH_ACCELERATOR_OFF

public static final int SEARCH ACCELERATOR OFF

To disable the DS2480B's search accelerator mode, place it into command mode, then use the message method to send it this value.

See Also:

Constant Field Values

Constructor Detail

DS2480B

Constructs a Uart to 1-Wire serial interface using the specified I/O pins for Uart communication between the DS2480B and the Javelin Stamp.

Parameters:

txPin - sends control messages and/or data messages to the DS2480B. Data messages are relayed to the 1-Wire bus by the DS2480B. Control messages are acted upon by the DS2480B. rxPin - receives control confirmations and/or data messages from the 1-Wire bus relayed by the DS2480B.

Method Detail

message

```
public void message(int b)
```

Sends a byte to the DS2480B.

Parameters:

b - the int value containing the byte sent to the DS2480B in its lower eight bits (least significant byte).

message

Sends a two message bytes to the DS2480B.

Parameters:

- b the int value containing the byte sent to the DS2480B in its lower eight bits (least significant byte).
- c the int value containing the byte sent to the DS2480B in its lower eight bits (least significant byte).

message

Sends a three message bytes to the DS2480B.

Parameters:

- b the int value containing the byte sent to the DS2480B in its lower eight bits (least significant byte).
- c the int value containing the byte sent to the DS2480B in its lower eight bits (least significant byte).
- d the int value containing the byte sent to the DS2480B in its lower eight bits (least significant byte).

message

Sends a specified number of message bytes from an array of int values.

Parameters:

```
number - of bytes from the array to be sent to the DS2480B. values - [] the int array containing the byte values to be sent to the DS2480B.
```

reset

```
public boolean reset()
```

Sends a reset pulse to the DS2480B's 1-Wire bus.

Returns:

true if a presence pulse was returned from the 1-Wire bus, false if a return pulse was not received from the 1-Wire bus.

getData

Retrieves data bytes from the 1-Wire bus and stores them in an array.

Parameters:

```
bytecount - the number of bytes to read from the 1-Wire bus.

array - [] the array of int values the bytes are to be stored in.

command - the message byte that causes the device on the 1-Wire bus to send the requested data.
```

getBit

```
public boolean getBit()
```

Reads a bit value from the 1-Wire bus.

Returns:

true if the bit value is 1, false if the bit value is 0.

strongPullup

```
public void strongPullup(int parameter)
```

Enables or disables the DS2480B's 4.7 k "strong pullup resistor".

Parameters:

parameter - byte value that enables or disables the pullup resistor. Use INFINITE_DURATION to enable and TERMINATE_DURATION to disable the pullup resistor.

Overview Package Class Use Tree Deprecated Index Help

Javelin Stamp

PREV CLASS NEXT CLASS
SUMMARY: NESTED | FIELD | CONSTR | METHOD

 FRAMES
 NO FRAMES
 All Classes

 DETAIL:
 FIELD | CONSTR | METHOD

Javelin Stamp is a trademark or registered trademark of Parallax, Inc. in the US and other countries. Copyright 2000-2002 Parallax, Inc. 599 Menlo Drive, Rocklin, California, 95765, U.S.A. All Rights Reserved.